



DOPAMINE LOCK

UI Design Documentation

Complete Screen Reference · Component System · Colour Palette

TEAM	Team Dobermans
PLATFORM	Android · Jetpack Compose
THEME	Dark Monochromatic
SCREENS	12 Screens · 22 Components
VERSION	v1.0.0

Colour System

Monochromatic Dark Palette

- DopamineBlack**
#000000 · Page backgrounds
- DopamineSurface**
#0A0A0A · Nav bar, status badges
- DopamineCard**
#111111 · Card backgrounds
- DopamineBorder**
#222222 · Card & field borders
- DopamineSubtle**
#333333 · Subtle accents
- DopamineDivider**
#1A1A1A · List dividers
- DopamineWhite**
#FFFFFF · Primary text, active icons
- DopamineGrey**
#B3B3B3 · Secondary text, labels
- DopamineDim**
#666666 · Muted / disabled text
- DopamineError**
#CF6679 · Danger only — Log Out, Abandon

DESIGN RULE

The only hue in the entire app is DopamineError (#CF6679).
It appears exclusively on destructive actions: Log Out and Abandon Mission.

Typography System

SansSerif · All-Caps Convention

headlineMedium

28sp · Bold
Screen titles

headlineSmall

24sp · SemiBold
Card titles, stat values

titleMedium

16sp · SemiBold
Row labels, nav items

labelLarge

14sp · Medium
Sub-headers — 1.25sp spacing

labelSmall

11sp · Medium
Badges, section labels — ALL CAPS

bodyMedium

14sp · Normal
Body copy, descriptions

bodySmall


12sp · Normal
Timestamps, subtitles

BUTTON OVERRIDE

All buttons: 13sp · Bold · ALL CAPS · letter-spacing 1.5sp
Height fixed at 52dp · Corner radius 8dp
No icon-only buttons — text is always present

01 Splash Screen

Entry · ~2.2 second fade-in



Full-screen im
ContentScale.

Animatable al
Of → 1f · 1200

Auto-nav after
Total display:

02 Onboarding

4-Page HorizontalPager · First Launch

DOPAMINE LOCK

Your Focus
Operating System

Block Distractions

Lock away apps that steal
your focus. Stay in control.

NEXT

SKIP

PAGES

Page 1	■ Block Dist
Page 2	■ Focus Dee
Page 3	■ Track Prog
Page 4	■ Build Disc

03 Authentication Screens

Login · Register · Forgot Password

DOPAMINE LOCK

Welcome Back

Sign in to continue

EMAIL

your@email.com

PASSWORD

Forgot Password?

SIGN IN

OR

CONTINUE WITH GOOGLE

CONTINUE WITH GOOGLE

DOPAMINE LOCK

Create Account

Start your journey

FULL NAME

John Doe

EMAIL

your@email.com

PASSWORD

CONFIRM PASSWORD

CREATE ACCOUNT

CANCEL

DOPAMINE LOCK

Reset Password

We'll send a reset link

EMAIL ADDRESS

your@email.com

SEND RESET LINK

04 Dashboard

GOOD MORNING

Aayush

A

TODAY'S STATS

4.2h
FOCUS HRS

6
SESSIONS

12
DAY STREAK

TODAY'S GOAL

DAILY FOCUS GOAL

70%

4 / 6 hours

QUICK ACTIONS

■ START FOCUS

■ MY TASKS

RECENT SESSIONS

✓ Deep Work — Code Review

52min

✓ Reading Session

30min

✓ Design Sprint

45min

■ Morning Focus Block

60min

✓ Documentation

25min

05 Focus Timer

Pomodoro · Canvas Arc · 3 States

←

FOCUS SESSION

IN PROGRESS

16:15

running

DEEP WORK

25-minute focus block

■ PAUSE

■ END

ENTER MISSION MODE

TIMER STATES

- Idle

[START SESSI
- Running

[PAUSE] [END
- Paused

[RESUME] [E

06 Mission Mode

Maximum Focus · No Bottom Nav

MISSION ACTIVE

MISSION MODE

Maximum focus. Zero distractions.

TIME ELAPSED

00:04:32

MISSION RULES

No social media or distracting apps

Notifications are silenced

Blocked apps cannot be accessed

Internet restricted to work tools only

Exiting mission mode is permanent

WARNING

Abandoning resets your streak. Cannot be undone.

ABANDON MISSION

07 Tasks Screen

Filter Chips · Priority Badges · FAB

MY TASKS

8 items

5 pending

ALL

PENDING

COMPLETED

■

Design system audit

Design

Today

HIGH

■

Write quarterly report

Work

Tmrw

HIGH

✓

Code review for PR #47

Development

Today

MEDIUM

■

Update dependencies

Development

Jun 25

LOW

✓

Morning meditation routine

Health

Daily

MEDIUM

Home

Focus

Tasks

Stats

Settings

+

08 Add / Edit Task

Category Grid · Priority Selector

←

NEW TASK

TASK TITLE
What needs to be done?

DESCRIPTION
Add details or notes...

CATEGORY

Work

Dev

Design

Health

Learn

Personal

DUE DATE
e.g. Jun 25, 2025

PRIORITY

High

Medium

Low

CREATE TASK

CANCEL

09 Analytics

Canvas Charts · No Third-Party Lib



10 Settings

SETTINGS

Preferences

A

Aayush

aayushdada01@gmail.com

12-DAY STREAK

>

ACCOUNT

■

Edit Profile

>

■

Change Password

>

■

Privacy & Security

>

FOCUS

■

Strict Focus Mode

■

Default Session

25 min

>

■

Break Duration

5 min

>

LOG OUT

DOPAMINE LOCK v1.0.0

Home

Focus

Tasks

Stats

Settings

11 Component System

Buttons · Cards · Fields · Navigation

DopamineButton

PRIMARY ACTION

SECONDARY ACTION

DANGER ACTION

Height: 52dp · Corner: 8dp
Font: 13sp · Bold · ALL CAPS
Letter spacing: 1.5sp
Primary: White fill, Black text
Secondary: Transparent, White border
Danger: #CF6679@15% fill, #CF6679 text

DopamineTextField

EMAIL
your@email.com

PASSWORD

Background: #111111 (DopamineCard)
Unfocused border: #222222
Focused border: #FFFFFF
Label: ALL CAPS · grey unfocused, white focused
Cursor: White

DashboardStatCard

4.2h
FOCUS HRS

Background: #111111 · Border: #222222
Value: 28sp Bold White
Label: 5.5sp · ALL CAPS · Grey · 1.2sp spacing

FocusProgressCard

DAILY FOCUS GOAL70%

4 / 6 hours

Track: #1A1A1A · Fill: White
Height: 4dp · Clipped rounded corners

Bottom Navigation Bar

HomeFocusTasksStatsSettings

Height: 64dp · Background: #0A0A0A
Top border: 1dp #222222
Active: filled icon + bold white label
Inactive: outlined icon + grey label
Indicator pill: Transparent (removed)


DopamineCard

Card Title

Background #111111 · Border #222222

Corner radius: 12dp
Elevation: 0dp (flat — no shadow)
Padding: 16dp

12 Navigation Architecture



ROUTE REFERENCE

"splash"	→ SplashScreen	"focus"	→ FocusTimerScreen
"onboarding"	→ OnboardingScreen	"mission"	→ MissionModeScreen
"login"	→ LoginScreen	"tasks"	→ TasksScreen
"register"	→ RegisterScreen	"add_task"	→ AddEditTaskScreen
"forgot_password"	→ ForgotPasswordScreen	"analytics"	→ AnalyticsScreen
"dashboard"	→ DashboardScreen	"settings"	→ SettingsScreen